

Softlock übertragen mit RUS-Tool

Vorbereitung

Stellen Sie sicher, dass auf dem neuen und dem alten Computer die aktuellen **Treiber** verwendet werden. Nutzen Sie folgenden Link, um die neuesten Treiber zu installieren:

http://download.dlubal.com/?file=Sentinel_LDK_GUI_setup.zip

Laden Sie sich dann das **RUS-Tool** herunter:


<http://download.dlubal.com/?file=RUS.exe>

Durchführung

Zielcomputer = NEUER Computer


Quellcomputer = ALTER Computer (mit aktivem Softlock)

1. Starten Sie das RUS-Tool auf Ihrem **Zielcomputer**. Wählen Sie im RUS-Dialog das Register *Transfer License*.



2. Definieren Sie den Pfadnamen der Ausgabedatei *.id mit der Empfängerinformation. Klicken Sie auf die Schaltfläche *Collect and Save Information*.

3. Starten Sie das RUS-Tool auf dem **Quellcomputer**. Klicken Sie auf das Register *Transfer License*.



RUS

Collect Status Information | Apply License File | **Transfer License**

To transfer (rehost) a license from one computer to another, you run the RUS program on both computers. On each computer, select the **Transfer License** tab and perform the appropriate step.

Collect information about the recipient computer

Step 1: On the computer to which you want to transfer the license (the "recipient computer"), collect and save information about the computer.

Save recipient information to ...

Collect and Save Information

Generate the license transfer file

Step 2: On the computer that currently contains the license (the "source computer"), select the license to transfer, read the recipient information file and generate a license transfer file.

Key Type	Key ID	Products
SL-AdminMode	XXXXXXXXXXXX	

Ihr aktiver Softlock

Zuvor erstellte Datei vom Quellcomputer

Read the recipient information file from ...

Generate the license transfer file to ...

Generate License Transfer File

- Wählen Sie die zu übertragende SL-Lizenz.
- Lesen Sie die Empfängerinformationsdatei (*.id) ein. Geben Sie den Ort der Ausgabe-Lizenztransferdatei (*.h2h) vor. Klicken Sie auf die Schaltfläche *Generate License Transfer File*.
- Starten Sie das Tool RUS.exe auf Ihrem Zielcomputer. Öffnen Sie das Register *Apply License File*.
- Laden Sie die Lizenztransferdatei (*.h2h) hoch. Klicken Sie auf die Schaltfläche *Apply Update*.
- Nun können Sie auf den Clients die Dlupal-Software starten und über das Menü *Hilfe > Autorisierung* die aktuelle **author.ini** Datei einlesen (auch im DEMO-Mode möglich). Nach dem Neustart der Software sind diese als Vollversionen verfügbar.

Ihr Team von DLUBAL SOFTWARE GMBH