

## 使用RUS-Tool 实现Dlubal软锁转移

请先通过此链接下载 RUS-Tool:

http://download.dlubal.com/?file=RUS.exe

目标电脑 = 新电脑

源电脑 = 旧电脑 (已激活软锁的电脑)

1. 先在目标电脑上打开RUS-Tool. 选择如下对话框的内容。

RUS				-		>	
Collect Status Information   transfer (rehost) a license fro mputers. On each computer, s	Apply License F m one computer elect the <b>Trans</b>	ile Transfer L to another, you fer License tab	icense   run the RUS and perforn	program on the appr	on both opriate st	ep.	
-Collect information about the	recipient compu	uter					
Step 1: On the computer to collect and save information	which you want about the comp	to transfer the lic uter.	ense (the "	recipient o	omputer")	,	
Save recipient information to	C:/Temp/red	C:/Temp/recipient.id					
		2	Collect a	nd Save Ir	nformation		
Кеу Туре Ке	ey ID	Products					
Кеу Туре Ке	ey ID	Products					
Read the recipient information	on file from					1	
Read the recipient information Generate the license transfe	n file from						
Read the recipient information Generate the license transfe	n file from		Generate	License Tr	  ansfer File		

2. 选择接收软锁的输出文件\*.id的路径名称。点击 Collect and Save Information.



3. 在源电脑上启动RUS工具。点击转移许可证标签 Transfer License.

🥐 RUS	0		-		$\times$					
Collect Status Information	Apply License File	Transfer License	1 3							
To transfer (rehost) a license	from one computer to an	other, you run the l	RUS program o	n both	1					
computers. On each computer, select the <b>Transfer License</b> tab and perform the appropriate step.										
Collect information about the recipient computer										
Step 1: On the computer to which you want to transfer the license (the "recipient computer"), collect and save information about the computer.										
Save recipient informatio	on to									
	,	Collo	ct and Save Tel	Formation	ill					
		Colle	ct and Save In	rormation	1					
Generate the license trans	sfer file									
Step 2: On the computer the license to transfer, re	that currently contains to ad the recipient information	he license (the "sou ion file and generat	rce computer") e a license tran	, select Isfer file.						
Key Type	Key ID	Products			пΙ					
SL-AdminMode	XXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXX				<u>'</u>					
激活的软锁										
				_						
	( 选择第二	步在目标电脑	  牛成的文化	4 ]						
					11					
Read the recipient inform	ation file from C:/Temp	/recipient.id								
Generate the license tran	sfer file to c./Temp/	license.h2h								
		5 Gener	ate License Tra	nsfer File						
		-								

- 4. 选择要转移的SL许可证。
- 5. 读取第二步生成的接收信息文件(\*.id)。选择输出许可转移文件(\*.h2h)的位置。

单击 "生成许可证传输文件Generate License Transfer File "按钮。

- 6. 在你的<mark>目标计算机</mark>上启动RUS.exe工具。打开 "应用许可证文件 Apply License File "选项卡。.
- 7. 导入第五步生成的许可证转移文件(\*.h2h)。点击 "应用更新 "按钮。
- 8. 现在启动Dlubal软件,通过帮助>授权(在DEMO模式下也可以)读取当前author.ini文件。
  重新启动软件,完整版可以使用了。